#### NAME

fusioninventory-agent\_windows-x64\_2.3.10.exe -- FusionInventory Agent 2.3.10 (x64 edition) Setup

#### SYNOPSTS

fusioninventory-agent\_windows-x64\_2.3.10.exe [/Option[ /Option[ ...]]]

#### DESCRIPTION

fusioninventory-agent\_windows-x64\_2.3.10.exe installs FusionInventory Agent 2.3.10 in your Microsoft Windows operative system.

fusioninventory-agent\_windows-x64\_2.3.10.exe has two types of installation; the from-scratch type, that allows to perform an installation of FusionInventory Agent from the beginning, based on the options' default values (see below), and the from-current-config type, that allows to perform an installation based on the options values of the FusionInventory Agent previously installed on the system, whether it exists (see /installtype). (Bear in mind that, with independence of the type of installation you choose, any existing release of FusionInventory Agent will be uninstalled automatically immediately before installing FusionInventory Agent 2.3.10)

**fusioninventory-agent\_windows-x64\_2.3.10.exe** also has two modes of installation; the *silent mode* (see /**S**), that allows to perform the installation of FusionInventory Agent in a non-interactive or unattended way, and the *visual mode*, that allows to perform the installation of FusionInventory Agent in a graphical and interactive way.

fusioninventory-agent\_windows-x64\_2.3.10.exe is provided with a series of options (see below) that allows to adapt the installation to practically any environment or need. To use these options properly it is essential to know the order in which values are taken into account. That order is as follows (the higher the number, the greater the priority).

- 0: Default values
- 1: Values from the current FusionInventory Agent (from-current-config installation type only)
- 2: Values from the command line
- 3: Values from graphic user interface (graphic mode installation only)

You should bear in mind the following when using the command line:

- \* There are two types of options; those that act as a switch (/option), and those that have a value (/option=value).
- \* The name of the options is case sensitive (/html is not the same that /HTML).
- \* The value of the options, unless otherwise specified, is not case sensitive ( $/local=C:\Temp$  is the same that  $/local=c:\temp$ ).
- \* In the options that have a value,
  - there should be no separation around the equal sign ( $/local = c: \land temp$  is incorrect).
- if the value contains a space or the (/) character, should go between single (') or double (") quotes ( $/local='C:\FusionInventory\ Agent'$ ).
  - if you want to set a empty value, you must indicate a empty string (/local = '').

These are the command line options available:

## /acceptlicense

You accept and acknowledge that you have read, and understood, the terms and conditions of FusionInventory Agent 2.3.10 license. (By default: No)

You must use this option if you perform the installation in silent mode (see  $/\mathbf{S}$ ).

If you indicate this option on the command line, but not the  ${\it /S}$  option, the  ${\it visual mode}$  installation will omit any question about the license.

## /add-firewall-exception

Adds FusionInventory Agent to the Windows Firewall exception list. (By default: No)

ToDo

## $\begin{tabular}{ll} \textbf{/backend-collect-timeout} = timeout \\ \end{tabular}$

Timeout for task **Inventory** modules execution. (By default: 180 seconds)

## /ca-cert-dir=pathname

Absolute path to the standard certificate directory of certificate authorities (CA). (By default: "")

The use of this option is incompatible with the use of the /ca-cert-file option. The /ca-cert-dir and /ca-cert-file options are mutually exclusive.

A standard certificate directory must contain the certificate files corresponding to different certificate authorities in Privacy Enhanced Mail (PEM) format, and their names must correspond to the hash value of the certificate's subject field, with extension \*.0.

For example, if you want to include the certificate file FICert\_Class1.crt in the directory pathname, you must calculate the hash value of the certificate's subject field using, for example, OpenSSL

C:\OpenSSL> openssl.exe x509 -in C:\FICert\_Classl.crt -subject\_hast -noout b760flce

and afterwards, move or copy the certificate file to the directory pathname with the name b760f1ce.0.

C:\OpenSSL> move.exe C:\FICert\_Class1.crt pathname\b760f1ce.0

#### /ca-cert-file=filename

Full path to the certificates file of certification authorities (CA). (By default: "")

The use of this option is incompatible with the use of the /ca-cert-dir option. The /ca-cert-dir and /ca-cert-file options are mutually exclusive.

filename must have extension \*.pem (Privacy Enhanced Mail) and can contain one or more certificates of certificate authorities. To concatenate multiple certificate files into one file you can make use, for example, of the command copy.

C:\> copy.exe FICert\_Class1.crt+FICert\_Class2.crt FICerts.pem

#### /ca-cert-uri=URI

 $\mathit{URI}$  from where to obtain the file or files of certificate of authorities (CA). (By default: "")

The use of this option requires the joint use of the  $\c/ca-cert-dir$  or  $\c/ca-cert-file$  options, but not both.

ToDo

#### /debug=level

Sets the debug level of the agent. (By default: 0)

level can be any of the following values:

- 0: Debug off
- 1: Normal debug
- 2: Full debug

# /delaytime=limit

Sets an initial delay before first contact with a remote destination (see /server). This delay is calculated at random between limit/2 and limit seconds. (Default: 3600 seconds)

This option is ignored for remote destinations after the first contact with each one, in favor of the specific server parameter (PROLOG\_FREQ).

The /delaytime option comes into play only if FusionInventory Agent runs in  $server\ mode$  (see /execmode).

## /dumphelp

See /help.

## /execmode=mode

Sets the agent execution mode. (By default:  ${\tt Current})$ 

mode can be any of the following values:

Service: The agent runs as a Windows Service (always running)

Task: The agent runs as a Windows Task (runs at intervals)

Manual: The agent doesn't run automatically (no Service, no Task)
Current: The agent runs in the same way that the agent already installed runs

The mode Service is known also as server mode.

The mode  ${\bf Task}$  is only available on Windows XP (or higher) and Windows Server 2003 (or higher) operative systems.

In the case of an installation **from-scratch** (see /installtype), the **Current** mode is a synonym of **Service**.

# /help

This help. If the /help option is present, shows the help and aborts the installation.

You could prefer make use of the /dumphelp option instead of the /help option to get information. The /dumphelp option creates a RTF file with this help, and aborts the installation.

## /html

Save the inventory as HTML instead of XML. (By default: No)

The /html option comes into play only if you have also indicated a value for the /local option.

## /httpd

This option is the opposite of /no-httpd. See /no-httpd for more information.

### /httpd-ip=ip

IP address by which the embedded web server should listen. (By default: 0.0.0.0)

#### /httpd-port=port

IP port by which the embedded web server should listen. (By default: 62354)

### /httpd-trust={ip|range|hostname}[,{ip|range|hostname}[...]]

Trusted IP addresses that do not require authentication token by the integrated web server. (By default: 127.0.0.1/32)

ip is an IP address in dot-decimal notation (ex. "127.0.0.1") or in CIDR notation (ex. "127.0.0.1/32")

range is an IP address range in dot-decimal notation (ex. "192.168.0.0 - 192.168.0.255" or "192.168.0.0 + 255") or in CIDR notation (ex. "192.168.0.0/24")

hostname is the name of a host (ex. "itms.acme.org")

Bear in mind that /httpd-trust does not have to include the hostname part of those URIs that are set up in /server because they are tacitly included. The following is an example; both configurations are equal.

```
/httpd-trust="127.0.0.1/32,itms.acme.org"
/server="http://itms.acme.org/glpi/plugins/fusioninventory/"
/httpd-trust="127.0.0.1/32"
/server="http://itms.acme.org/glpi/plugins/fusioninventory/"
```

### /installdir=pathname

Sets the installation base directory of the agent. (By default: C:\Program Files \FusionInventory-Agent)

pathname must be an absolute path.

ToDo

# /installtasks={task[,task[...]]|macro}

Selects the tasks to install. (By default: Default)

task can be any of the following values:

Deploy: Task Deploy
ESX: Task ESX

Inventory: Task Inventory
NetDiscovery: Task NetDiscovery
NetInventory: Task NetInventory
WakeOnLan: Task WakeOnLan

There are three macros defined to simplify the mission, are the following:

Minimal: Inventory
Default: Inventory

Full: Deploy, ESX, Inventory, NetDiscovery, NetInventory, WakeOnLan

It should be noted that the **Inventory** task will be always installed and that the **NetDiscovery** and **NetInventory** tasks are inter-dependent. Nowadays **Minimal** and **Default** are the same configuration.

# /installtype={from-scratch|from-current-config}

Selects between an installation from the beginning (**from-scratch**) or, whether the system has a previously installed agent, an installation based on the current configuration (**from-current-config**). (By default: **from-current-config**)

The installer automatically switches from **from-current-config** to **from-scratch** whether it's not able to detect a FusionInventory Agent previously installed on the system. This behaviour makes unnecesary to have to indicate **/installtype=from-scratch** to perform a FusionInventory Agent installation on those systems in which it doesn't exist previously and, at the same time, facillitates the update of FusionInventory Agent on those systems in which it exists.

## /local=pathname

Writes the results of tasks execution into the given directory. (By default: "")

You must indicate an absolute pathname or an empty string (""). If you indicate an empty string, the results of tasks execution will not be written locally.

You can use the /local and /server options simultaneously.

```
/logfile=filename
    Writes log messages into the file filename. (By default: C:\Program Files\FusionInventory-
    Agent\fusioninventory-agent.log)
    You must indicate a full path in filename. The /local option comes into play only if you have
    also indicated File as a value of the /logger option.
/logfile-maxsize=size
    Sets the maximum size of logfile (see /logfile) to size . (By default: 16 MBytes)
/logger=backend[.backend]
    Sets the logger backends. (By default: File)
   backend can be any of the following values:
          File: Sends the log messages to a file (see /logfile)
          Stderr: Sends the log messages to the console
/no-category=category[, category[...]]
   Do not inventory the indicated categories of elements. (By default: "")
    category can be any of the following values:
          Environment: Environment variables
          Printer: Printers
          Process: System's processes (has no effect on Microsoft Windows systems)
          Software: Software
          User: Users
   If you indicate an empty string (""), all categories of elements will be inventoried.
/no-html
   This option is the opposite of /html. See /html for more information.
   Disables the embedded web server. (By default: No)
/no-p2p
   Do not use peer to peer to download files. (By default: No)
/no-scan-homedirs
    This option is the opposite of /scan-homedirs. See /scan-homedirs for more information.
/no-scan-profiles
   This option is the opposite of /scan-profiles. See /scan-profiles for more information.
/no-ssl-check
    Do not check server certificate. (By default: No)
/no-start-menu
   Do not create the FusionInventory Agent folder on the Start Menu. (By default: No)
   The FusionInventory Agent folder, whether it is created, it is for all users.
/no-task=task[,task[...]]
   Disables the given tasks. (By default: "")
    task can be any of the following values:
          Deploy: Task Deploy
          ESX: Task ESX
          Inventory: Task Inventory
          NetDiscovery: Task NetDiscovery
          NetInventory: Task NetInventory
          WakeOnLan: Task WakeOnLan
    If you indicate an empty string (""), all tasks will be executed.
/p2p
   This option is the opposite of /no-p2p. See /no-p2p for more information.
/password=password
   Uses password as password for server authentication. (By default: "")
    The /password comes into play only if you have also indicated a value for the /server option.
/proxy=URI
   Uses URI as HTTP/S proxy server. (By default: "")
   Launches the agent immediately after its installation. (By default: No)
```

/S

Silent installation. (By default: No)

You must accept the license in a explicit way (see /acceptlicense) if you perform the installation in silent mode.

#### /scan-homedirs

Allows the agent to scan home directories for virtual machines. (By default: No)

#### /scan-profiles

Allows the agent to scan user profiles for software. (By default: No)

## /server=URI[,URI[...]]

Sends results of tasks execution to given servers. (By default: "")

If you indicate an empty string (""), the results of tasks execution will not be written remotely.

You can use the /server and /local options simultaneously.

#### /ssl-check

This option is the opposite of /no-ssl-check. See /no-ssl-check for more information.

#### /start-menu

This option is the opposite of /no-start-menu. See /no-start-menu for more information.

#### /tag=tag

Marks the computer with the tag tag . (By default: "")

#### /task-daily-modifier=modifier

Daily task schedule modifier. (By default: 1 day)

modifier can take values between 1 and 30, both included.

The /task-daily-modifier option comes into play only if you have also indicated Daily as value of the /task-frequency option.

### /task-frequency=frequency

Frequency for task schedule. (By default: Hourly)

frequency can be any of the following values:

Minute: At minute intervals (see option /task-minute-modifier)
Hourly: At hour intervals (see option /task-hourly-modifier)
Daily: At day intervals (see option /task-daily-modifier)

## /task-hourly-modifier=modifier

Hourly task schedule modifier. (By default: 1 hour)

modifier can take values between 1 and 23, both included.

The /task-hourly-modifier option comes into play only if you have also indicated Hourly as value of the /task-frequency option.

# /task-minute-modifier=modifier

Minute task schedule modifier. (By default: 15 minutes)

modifier can take the following values: 15, 20 or 30.

The /task-minute-modifier option comes into play only if you have also indicated Minute as value of the /task-frequency option.

## /timeout=timeout

Sets the limit time (in seconds) to connect with the server. (By default: 180 seconds)

The /timeout option comes into play only if you have also indicated a value for the /server option.

# /user=user

Uses user as user for server authentication. (By default: "")

The /user option comes into play only if you have also indicated a value for the /server option.

# EXAMPLES

ToDo

# VERSION

This help is current for version 2.2.9903 of FusionInventory Agent's installer for Microsoft Windows.

## REPORTING BUGS

User Mailing List

http://lists.alioth.debian.org/mailman/listinfo/fusioninventory-user

Devel Mailing List

Project Manager

http://forge.fusioninventory.org/projects/fusioninventory-agent-windows-installer

### COPYRIGHT

Copyright 2012-2013 FusionInventory Team. GNU GPL version 2 or (at your option) any later version <a href="http://www.gnu.org/licenses/old-licenses/gpl-2.0-standalone.html">http://www.gnu.org/licenses/old-licenses/gpl-2.0-standalone.html</a>. This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

## SEE ALSO

FusionInventory Web Site http://www.fusioninventory.org/

#### AUTHOR

Tomás Abad <tabadgp@gmail.com>